

XPS snapshot compatibility

Release note of the 9th October 2023

Latest modifications added on the new XPS controller revisions involved a snapshot compatibility break. New snapshot cannot be installed on previous controller versions and previous snapshots cannot be installed on latest controllers.

See below details on snapshot compatibilities.

- **XPS-D**
 - **Serial number \geq 22308106**
 - These controllers are compatible with snapshot **XPS-D-USB_N131xx**.
 - **Serial number \leq 22308105**
 - These controllers are compatible with snapshot **XPS-D_N130xx**.
- **XPS-RLD**
 - **Serial number \geq 22348036**
 - These controllers are compatible with snapshot **XPS-RL-D-USB_N161xx**.
 - **Serial number \leq 22348035**
 - These controllers are compatible with snapshot **XPS-RL-D_N160xx**.
- **HXP-D**
 - **HXP50-D**
 - **Serial number \geq 22362019**
 - These controllers are compatible with snapshot **HXP-D-USB_N501xx**.
 - **Serial number \leq 22362018**
 - These controllers are compatible with snapshot **HXP-D_N500xx**.
 - **HXP100-D**
 - **Serial number \geq 22363008**
 - These controllers are compatible with snapshot **HXP-D-USB_N501xx**.
 - **Serial number \leq 22363007**

- These controllers are compatible with snapshot **HXP-D_N500xx**.
- HXP100P-D
 - **Serial number >= 23364002**
 - These controllers are compatible with snapshot **HXP-D-USB_N501xx**.
 - **Serial number <= 23364001**
 - These controllers are compatible with snapshot **HXP-D_N500xx**.
- HXP200-D
 - **Serial number >= 22365006**
 - These controllers are compatible with snapshot **HXP-D-USB_N501xx**.
 - **Serial number <= 22365005**
 - These controllers are compatible with snapshot **HXP-D_N500xx**.
- HXP200S-D
 - **Serial number >= 22366002**
 - These controllers are compatible with snapshot **HXP-D-USB_N501xx**.
 - **Serial number <= 22366001**
 - These controllers are compatible with snapshot **HXP-D_N500xx**.
- HXP1000-D
 - **Serial number >= 23367001**
 - These controllers are compatible with snapshot **HXP-D-USB_N501xx**.
 - **Serial number <= 22367001**
 - These controllers are compatible with snapshot **HXP-D_N500xx**.

If you try to install a snapshot that is not compatible with your controller, the installation will be aborted, and the controller will return to its pre-installation state.

The support of previous generation's snapshots (**130xx**, **160xx** and **500xx**) will continue but they will not be enhanced with new features.